



Film Development

1. Mix developer with the right quantity of water and make sure the other chemicals are ready to be used. Wear gloves.




You can pour it straight from the bottle. Doesn't need to be measured. Doesn't need to be at 20 degrees. Put back in the bottle (use a funnel) after use.

You can pour it straight from the bottle. Doesn't need to be measured. Doesn't need to be at 20 degrees. Put back in the bottle (use a funnel) after use.

You only need a few drops at the end. Mix with water and soak film for 30 seconds. Discard after use.

For each 35mm film you need 40ml of developer to 280ml of water. Make sure is at 20 degrees. Discard after use.

2. Load film onto reel (in the dark!)




Make sure you have all the equipment you need with you in the film development room or inside the black bag.

Open the film canister (either unscrew the lid or use a bottle opener depending on the type of canister). Roll film onto reel.




3. Make the tank lightproof by putting the reels onto the column and then putting the reels into the tank. Lock the lightproof lid on top.

IN THE DARK



4. DEVELOPER




1
For each 35mm film you need 40ml of developer and 280ml of water. Make sure is at 20 degrees.



2
Open plastic lid



3
Open plastic lid



4
Start timer



5
Close plastic lid



6
Agitate for 10 seconds every minute.



7
When the timer goes off, open plastic lid and throw away the developer (in the sink).

Quickly pour in Stopbath

5. STOPBATH



1
Pour stopbath straight into the tank. No need to mix. Stop when the tank is full.



2
Close plastic lid.



3
Agitate continuously for 30 seconds.



4
Pour back into bottle.

Pour in fixer

6. FIXER



1
Pour FIXER straight into the tank. No need to mix. Stop when the tank is full.



2
Close plastic lid.



3
Agitate for 10 seconds and then leave to rest for 5 minutes.



4
Pour back into bottle.



7. WASH FILM




1
Place water hose into tank and turn on cold water.



2
Wait 10 minutes.



3
Add a few drops of wetting agent.



4
Top up with water and soak film for 30 seconds.


8. DRY FILM



1
Remove film from spiral



2
Hang film up to dry in the drying cabinet. Clip it at the top and bottom.



3
When dry, cut into strips and store in negative files.